

# ESBHA001 Server User Manual

---

Version: 0.3

## Copyright Notice

This document contains proprietary and confidential data owned by ALCODEX, its clients and partners. The information contained herein shall not be copied, reproduced in using any means or manner, in part or full without the written consent of ALCODEX limited. Use of the data herein for any purpose other than intended is forbidden.

## Document Control Data Sheet

| Document information  |                                  |
|-----------------------|----------------------------------|
| Classification        | Confidential                     |
| Document Name         | ESBHA001 Server User Manual      |
| Document Issue No.    | 0                                |
| Document Revision No. | 3                                |
| Document Id           | ATPL/SVR/MNL/19/02/2020-1        |
| Document Issue date   | 01/02/2020                       |
| Prepared by           | Alan Henry                       |
| Reviewed By           | Veena G                          |
| Approved By           |                                  |
| Distribution List     | Alcodex Technologies Private Ltd |

## Contents

|     |                             |    |
|-----|-----------------------------|----|
| 1.0 | ESBHA001 SERVER MANUAL..... | 4  |
| 1.1 | LOGIN PAGE.....             | 4  |
| 1.2 | HOME .....                  | 4  |
| 1.3 | DASHBOARD.....              | 5  |
| 1.4 | DATA ANALYSIS .....         | 6  |
| 1.5 | ALARM MANAGEMENT .....      | 11 |
| 1.6 | ACTIVE ALARMS .....         | 12 |
| 1.7 | DEVICE MANAGEMENT.....      | 13 |
| 1.8 | USER MANAGEMENT .....       | 15 |
| 1.9 | API-FAQ.....                | 17 |

## 1.0 ESBHA001 Server Manual

### 1.1 Login Page

To access the ESBHA001 server, enter a valid IP address: https://IP-address:port-number. It then redirects to the login page of the server.



Fig-1.1 - Login

- 1) Enter username
- 2) Enter password
- 3) Login

### 1.2 Home



Fig-1.2 - Home

- 1) To select navigation bar (refer fig 1.2)
- 2) To view data analysis
- 3) To view dashboard

Navigation bar comprises of:

| Module                            | Description                                     |
|-----------------------------------|---|
| <a href="#">Home</a>              | directs to the home page                        |
| <a href="#">Live data</a>         | directs the homepage to the data analysis page. |
| <a href="#">Alarm management</a>  | directs to the alarm management page.           |
| <a href="#">Active alarms</a>     | directs to the active alarms page.              |
| <a href="#">Device management</a> | directs to device management page.              |
| <a href="#">User management</a>   | directs to user management page.                |
| <a href="#">API FAQ</a>           | directs to API-FAQ page                         |

### 1.3 Dashboard

The dashboard helps to view device's information, Air Quality Index (AQI) and its corresponding graph. To view the data of a device, click on the location marker in the map, such that it shows the data like device location ,average, min, max and graph of each parameter. Color coding of each parameter is based on CPCB (Central Pollution Control Board) guidelines.




Fig-1.3 - Dashboard

- 1) Device Id and location of the device
- 2) Max, min and average values of parameters
- 3) Air Quality Index (AQI) and its graph
- 4) Parameter's graph
- 5) Location marker of the selected device in the map

#### 1.4 Data analysis

Data analysis contains the following subsections:

##### 1) Device status table

The device status table indicates the Device Id, Family, Subtype, City, Landmark and shows whether the device is live or not. To see each device's raw data (live data), click on a device row in the device status table, thus the data appears in the raw data table and data statistics table.




Fig 1.4(a) - Live data

- 1) Device status table
- 2) Shows whether the device is live or not. If yellow (●) is indicated, the device is offline. If its green (●) color, then the device is online
- 3) The selected device is highlighted

## 2) Raw data

For a selected device in the device status table, the raw data section allows the user to look at the individual data of each parameter. If no date is specified, then the data will be the latest data sent by the sensor.

Raw data encompasses three sections:

### a) Raw data table view:

Raw data table exhibits different parameters values and their units. It also displays the AQI (Air Quality Index) values of each device.

| Temperature (°C) | Pressure (hPa) | Humidity (%) | PM10 (µg/m³) | PM2.5 (µg/m³) | CO (PPM) | NO2 (PPM) | SO2 (PPM) | CO2 (PPM) | Received Time     | AQI () |
|------------------|----------------|--------------|--------------|---------------|----------|-----------|-----------|-----------|-------------------|--------|
| 26.7             | 968.69         | 100.00       | 23.86        | 22.17         | 0.075    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:45:36 | 37     |
| 26.7             | 968.65         | 100.00       | 23.73        | 22.21         | 0.074    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:44:35 | 37     |
| 26.7             | 968.65         | 100.00       | 24.41        | 22.76         | 0.077    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:43:31 | 38     |
| 26.7             | 968.67         | 100.00       | 24.76        | 23.21         | 0.078    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:42:29 | 39     |
| 26.7             | 968.66         | 100.00       | 24.79        | 22.76         | 0.073    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:41:28 | 38     |
| 26.7             | 968.65         | 100.00       | 24.30        | 22.20         | 0.073    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:40:25 | 37     |
| 26.7             | 968.64         | 100.00       | 22.72        | 21.75         | 0.070    | 0.006     | 0.002     | 0.000     | 2019/0/28 5:39:23 | 36     |
| 26.7             | 968.62         | 100.00       | 22.65        | 21.88         | 0.066    | 0.006     | 0.001     | 0.000     | 2019/0/28 5:37:24 | 36     |
| 26.7             | 968.61         | 100.00       | 22.06        | 21.18         | 0.060    | 0.006     | 0.001     | 0.000     | 2019/0/28 5:36:21 | 35     |

*Fig-1.4(b) – Raw data table*

1) Date selection text box: By selecting a specific date, the table shows the data on that date. In case, if the data on specified date is not available, then the table shows the date in which the previous data has arrived.

2) Raw data table

3) Refresh table button

### b) Raw data chart view:

It gives the graphical representation of the raw data based on the parameter selection option. Depending on the parameter, the graph varies.




Fig-1.4(c) – Raw data chart

- 1) Parameter selection dropdown
- 2) Graph-based on the parameter selection
- 3) X-axis shows Received time
- 4) Y-axis shows Parameters Raw data

c) Raw data download:

Data can be downloaded by specifying the start date and end date. Downloaded data will be in CSV (Comma Separated Value) file format.

Fig-1.4(d) – Raw data download



- 1) Start date
- 2) End date
- 3) File format selection
- 4) Download

### 3) Data statistical value

The statistical data of the selected device in specific time frame can be viewed in:

Data statistics table:

It illustrates different parameters and their statistical values such as max, min, average and sample count of a parameter. Time frame comprises of:

- a) daily: shows the statistical data on daily basis
- b) monthly: shows statistical data on monthly basis
- c) yearly: shows the statistical data on yearly basis

**Data Statistics**

Table View | Chart | Download | Time Frame: Daily

Select Parameter

| Parameter   | Unit  | Samples Count | Min    | Max     | Average | Date      |
|-------------|-------|---------------|--------|---------|---------|-----------|
| Temperature | °C    | 83            | 39.8   | 46.9    | 43.3    | 29.4.2019 |
| Pressure    | hPa   | 83            | 979.70 | 1000.31 | 990.11  | 29.4.2019 |
| Humidity    | %RH   | 83            | 1      | 21.94   | 8.01    | 29.4.2019 |
| PM2.5       | µg/m³ | 83            | 224.25 | 374.08  | 277.51  | 29.4.2019 |
| PM2.5       | µg/m³ | 83            | 55.08  | 125.78  | 81.13   | 29.4.2019 |
| CO          | PPM   | 83            | 0      | 1.816   | 0.897   | 29.4.2019 |
| NO2         | PPM   | 83            | 0.021  | 0.025   | 0.023   | 29.4.2019 |
| SO2         | PPM   | 83            | 0      | 0.008   | 0.004   | 29.4.2019 |

Page 100 | Previous | Next

Fig 1.4(e) – Statistics table

- 1) To select parameter in order to show their statistical data
- 2) To select a time frame
- 3) Data statistics table

### a) Data statistics chart

It gives the graphical representation of the statistical data. Graphs are shown based on the parameter selected. The time frame option is used to select the data on daily, monthly or yearly basis. The select function consists of:

- a) count
- b) max
- c) min

Confidential

d) average

Based on the option selected from the select function dropdown, it shows different graphs.




Fig 1.4(f) – Statistics chart

- 1) Parameter selection dropdown
- 2) Select function dropdown: To select max, min, average or count
- 3) To select time frame options
- 4) Graph based on the parameter selection and select function dropdown

b) Download in CSV (Comma Separated Value) format

Data can be downloaded by specifying the start date and end date. Downloaded data will be in CSV (Comma Separated Value) format.

Fig 1.4(g) – Statistics download

- 1) To select a specific start date
- 2) To select a specific end date
- 3) To select time frame
- 4) File format selection
- 5) Download

### 1.5 Alarm management

The main purpose of alarm management is to manage alarms and to spawn or delete alarm rules. Each data is then compared with the threshold value set by the authorized user. If the value exceeds or less than the threshold value, then an alarm will be generated. There are two types of clearing modes:

- i. Time-based mode: Time-based clearing mode makes an alarm active within the time interval given by the users in seconds.
- ii. Manual mode: Manual clearing mode makes an alarm active until an user clears an alarm on an active alarms page.




Fig 1.5(a) – Alarm management

- 1) To delete an alarm rule
- 2) To edit an alarm rule information
- 3) An alarm rule is highlighted
- 4) To add a new alarm rule

**To add a new alarm rule in alarm management:**

| Device Id | City | Zone | Parameter   | Unit  | Min Limit | Max Limit |
|-----------|------|------|-------------|-------|-----------|-----------|
|           |      |      | Temperature | oC    |           |           |
|           |      |      | Pressure    | hPa   |           |           |
|           |      |      | Humidity    | %RH   |           |           |
|           |      |      | PM10        | ug/m3 |           |           |
|           |      |      | PM2P5       | ug/m3 |           |           |
|           |      |      | CO          | PPM   |           |           |
|           |      |      | NO2         | PPM   |           |           |

*Fig 1.5(b) – Rule adding section*

Steps:

- 1) Enter rule name
- 2) Select device type
- 3) Select a clearing mode option
- 4) Enter time in seconds, if the clearing mode is time-based
- 5) Give a brief description about rule
- 6) Set minimum and maximum threshold for different parameters
- 7) Click add rule button
- 8) Select the device where the alarm rule should be applicable

## 1.6 Active Alarms

This page gives the alarms that are generated based on comparing the posted data with the threshold value. The clear option is available in order to clear an alarm. It gives the information about the device's location, device id and the alarm generated. The filter option is available to filter out alarms based on the alarm names. If the filter option is not specified, then it shows all the alarms generated.

Envius IoT Suite

Active Alarms

Table below shows the latest alarms generated

Filter By Alarm [All] -

| No. | Alarm Name | Time Stamp  | Logs                              |
|-----|------------|---|-----------------------------------|
| 1   | rule 1     | Tue Jan 28 2020 15:16:31 GMT+0530 (India Standard Time) | Device id: test1; Location: kochi |

Clear Alarm

Active

Fig 1.6 – Active alarms

- 1) Gives device Id and device location
- 2) Filter option
- 3) Timestamp at which alarm is generated
- 4) A generated alarm rule
- 5) Status of alarm
- 6) Clear alarm option

## 1.7 Device management

The main feature of device management is to add, edit or delete devices. Consist of two subsections:

### a) Installed devices

It's a table that encompasses values such as device id, type, family, subtype, remove and edit button.




Fig 1.7(a) – Device management

- 1) To remove a device from the server
- 2) To edit device information
- 3) Device location

#### b) Device adding

Devices can be added to the server by giving information such as device Id, subtype, family, etc. Device adding section comprises of two sections:

- 1) Device deployment settings
- 2) Device parameter settings

The device deployment details section is used to add details of customer name, landmark, city, latitude, and longitude.

**To add a new device:**

**Add New Device**

Device Id\*  Type\*  Family\*  Sub Type\*  Time Zone\*

**Deployment Details**

Customer Name\*  Lot Number\*  Serial Number\*  Grade\*

Deployment\*  City\*  Zone\*  Landmark\*  Latitude\*  Longitude\*

Description

*Fig 1.7(b) – device adding to the server*

Steps to add a new device to the server:

- 1) Device Id can contain alphanumeric characters (A-Z, a-z,0-9) and space. It must be between 3 to 20 characters long.
- 2) Select a type
- 3) Pick a suitable family type
- 4) Select the subtype
- 5) Select the time zone
- 6) Customer name can contain alphabets (A-Z, a-z). Must be between 3 to 20 characters long.
- 7) Lot number
- 8) Serial number
- 9) Select the grade and deployment
- 10) Enter city, landmark, zone. It can contain alphabets (A-Z, a-z), space and can be 3 to 20 characters long.
- 11) Enter the latitude and longitude. Latitude and longitude accept numbers only.
- 12) Click the add device button to save the device details to the server.


## 1.8 User management

- 1) Users can add and delete user information.
- 2) User roles supported will be administrator, supervisor, and operator.

**User privileges:**

| Modules           | Admin | Supervisor | Operator |
|-------------------|-------|------------|----------|
| Dashboard         | ✓     | ✓          | ✓        |
| Home page         | ✓     | ✓          | ✓        |
| Live data         | ✓     | ✓          | ✓        |
| Alarm management  | ✓     | ✓          | ✗        |
| Active alarms     | ✓     | ✓          | ✓        |
| Device management | ✓     | ✓          | ✗        |
| User management   | ✓     | ✗          | ✗        |
| API-FAQ           | ✓     | ✓          | ✓        |

*Table 1.8 – User privileges*



*Fig 1.8(a) – User management*

- 1)To add a new user
- 2)To remove user
- 3)User table



**To add a new User:**

*Fig 1.8(b) -user management*


**Steps:**

- 1) Enter the name of the user. Name can contain capital and small alphabets. Limit of the name should be between 3 to 20
- 2) Enter a valid email
- 3) Provide a 10-digit valid contact number of the user
- 4) Select the role of the user, for further details refer *Table 1.8*
- 5) Enter the username. Username can contain capital or small alphabets and maximum length should be greater than 5.
- 6) Enter password. Password Length should be greater than 6.
- 7) Confirm password
- 8) Press the Save button to save the user to the server.

**1.9 API-FAQ**

API-FAQ gives the description of the APIs (Application Programming Interface) that the approved users can access.

Envitus IoT Suite



API

API Description

Approved users of the Envitus IoT Suite API can access the following details:

- /device/sensor/livedata/v1
- /device/sensor/livedata/v1/count
- /device/sensor/stats/v1
- /device/sensor/stats/v1/count

Request API Access

Envitus grants only a limited number of API keys, and allow access to the Content API for purposes of:

*Third Party integrations for immediate client only*

Envitus grants only a limited number of API keys, and does not allow access to the Content API for purposes of:

- Academic research
- Any use not associated with a client application

API key will allow limited access of 500 calls per-day/ per device to the API - this key is to be used for development purposes only.

The API key is provided to the concerned authority on premise installation.

Documentation

| No | API URL                       | Comments   |
|----|-------------------------------|--|
| 1  | /device/sensor/stats/v1       | Use this API to return the daily/monthly/yearly statistics data for a device.<br>Statistics data includes will include min, max, number of packets received for each device parameter. |
| 2  | /device/sensor/stats/v1/count | Use this API to get the total number of data statistics captured for given devices   |

Fig1.9 - API-FAQ